

如何用MDS增加一個新的libipmipar的package

0. 例如:建立multi-platform, 例如FH-C612NM有很多platform. (MB,2U8,2U12....),或是要更换 platform名字




1. 在要新增的project上按右鍵,New->Other-> MegaRacDev.....->SPX->Duplicate spx package ->next ->選取要複製的package->並改Target Project Name




2. 改spx name (右鍵按下Rename)

10.194.49.234:3000/s/S1EuwbPTI 1/4




需修改成與PROJECT同名,還有下面的package name 要修改




然後 到Binary Packages,因為已經修改了folder名,所以要修改這裡的路徑

10.194.49.234:3000/s/S1EuwbPTI 2/4




改好後




3. 右側script: 修改成要新增的pack名 (可參考圖中紅色部分) Dev-install:

10.194.49.234:3000/s/S1EuwbPTI 3/4



Rules



4. 然後按 Create SPX Package



5. 確定了package建好 (會在你duplicate的package的資料夾位置)‧到該位置的MDS project 下,右鍵去Update latest package, PRJ內的Platform configuration內應可看到要新加的 platform,

視用途決定要用multi-platform或是single.

Multi的話,記得到PlatformHook.c內的PDK_PlatformID()去做修改,決定如何切換platform.

10.194.49.234:3000/s/S1EuwbPTI